

Getting Started Guide

/ ForgeRock Identity Gateway 5.5

Latest update: 5.5.2

ForgeRock AS 201 Mission St., Suite 2900 San Francisco, CA 94105, USA +1 415-599-1100 (US)

www.forgerock.com

Copyright © 2017 ForgeRock AS.

Abstract

Quick introduction to ForgeRock® Identity Gateway for new users and readers evaluating the product.



This work is licensed under the Creative Commons Attribution-NonCommercial-NoDerivs 3.0 Unported License.

To view a copy of this license, visit https://creativecommons.org/licenses/by-nc-nd/3.0/ or send a letter to Creative Commons, 444 Castro Street, Suite 900, Mountain View, California, 94041, USA.

ForgeRock® and ForgeRock Identity Platform™ are trademarks of ForgeRock Inc. or its subsidiaries in the U.S. and in other countries. Trademarks are the property of their respective owner

UNLESS OTHERWISE MUTUALLY AGREED BY THE PARTIES IN WRITING, LICENSOR OFFERS THE WORK AS-IS AND MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND CONCERNING THE WORK, EXPRESS, IMPLIED, STATUTORY OR OTHERWISE, INCLUDING, WITHOUT LIMITATION, WARRANTIES OF ITILE, MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, NONINFRINGEMENT, OR THE ABSENCE OF LATENT OR OTHER DEFECTS, ACCURACY, OR THE PRESENCE OF ABSENCE OF ERRORS, WHETHER OR NOT DISCOVERABLE. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO SUCH EXCLUSION MAY NOT APPLY TO YOU.

EXCEPT TO THE EXTENT REQUIRED BY APPLICABLE LAW, IN NO EVENT WILL LICENSOR BE LIABLE TO YOU ON ANY LEGAL THEORY FOR ANY SPECIAL, INCIDENTAL, CONSEQUENTIAL, PUNITIVE OR EXEMPLARY DAMAGES ARISING OUT OF THIS LICENSE OR THE USE OF THE WORK, EVEN IF LICENSOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

DoinVn Font

Bitstream Vera Fonts Copyright

Copyright (c) 2003 by Bitstream, Inc. All Rights Reserved. Bitstream Vera is a trademark of Bitstream, Inc.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software typefaces.

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Bitstream" or the word "Vera".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Bitstream Vera" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself.

THE FONT SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRIGHT, PATENT, TRADEMARK, OR OTHER RIGHT. IN NO EVENT SHALL BITSTREAM OR THE GNOME FOUNDATION BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE.

Except as contained in this notice, the names of Gnome, the Gnome Foundation, and Bitstream Inc., as hall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from the Gnome Foundation or Bitstream Inc., respectively. For further information, anomed oft org.

Arey Fonts Convright

Copyright (c) 2006 by Tavmjong Bah. All Rights Reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the modifications to the Bistream Vera Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software typefaces

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Tavmjong Bah" or the word "Arev".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Tavmjong Bah Arev" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself.

THE FONT SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRIGHT, PATENT, TRADEMARK, OR OTHER RIGHT. IN NO EVENT SHALL TAVMJONG BAH BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE OR FROM OTHER DEALINGS IN THE FONT SOFTWARE.

Except as contained in this notice, the name of Tavmjong Bah shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from Tavmjong Bah. For further information, contact: tavmjong @ free . fr.

FontAwesome Copyright

Copyright (c) 2017 by Dave Gandy, http://fontawesome.io.

 $This \ Font \ Software \ is \ licensed \ under \ the \ SIL \ Open \ Font \ License, \ Version \ 1.1. \ See \ https://opensource.org/licenses/OFL-1.1.$



Table of Contents

Preface	
1. About This Guide	iv
2. Formatting Conventions	
3. Accessing Documentation Online	v
4. Using the ForgeRock.org Site	
5. Getting Support and Contacting ForgeRock	v
1. IG At a Glance	
2. First Steps	
2.1. Software Requirements	
2.2. Configuring the Network	
2.3. Installing IG	
2.4. Installing the Sample Application	
2.5. Trying IG With a Simple Configuration	7
2.6. Adding a Route to the IG Configuration	
3. Configuring Routes With IG Studio	12
3.1. Accessing IG Studio	
3.2. Creating Simple Routes	
3.3. Deploying Routes to Your Configuration	
3.4. Adding Filters to a Route	16
3.5. Editing and Redeploying Routes	
3.6. Importing Routes Into IG Studio	18
3.7. Viewing and Searching for Routes in Your Configuration	19



Preface

ForgeRock Identity Platform™ serves as the basis for our simple and comprehensive Identity and Access Management solution. We help our customers deepen their relationships with their customers, and improve the productivity and connectivity of their employees and partners. For more information about ForgeRock and about the platform, see https://www.forgerock.com.

1. About This Guide

IG integrates web applications, APIs, and microservices with the ForgeRock Identity Platform, without changing the application or container where they run. Based on reverse proxy architecture, it enforces security and access control in conjunction with AM modules.

This guide can help access management designers and administrators to install IG with a basic configuration, and start using the basic features of IG quickly and easily.

This guide assumes basic familiarity with the following topics:

- HTTP, including how clients and servers exchange messages, and the role that a reverse proxy (gateway) plays
- JSON, the format for IG configuration files
- Managing services on operating systems and application servers
- Configuring network connections on operating systems

2. Formatting Conventions

Most examples in the documentation are created in GNU/Linux or Mac OS X operating environments. If distinctions are necessary between operating environments, examples are labeled with the operating environment name in parentheses. To avoid repetition file system directory names are often given only in UNIX format as in /path/to/server, even if the text applies to C:\path\to\server as well.

Absolute path names usually begin with the placeholder /path/to/. This path might translate to /opt/, C:\Program Files\, or somewhere else on your system.

Command-line, terminal sessions are formatted as follows:

\$ echo \$JAVA_HOME
/path/to/jdk



Command output is sometimes formatted for narrower, more readable output even though formatting parameters are not shown in the command.

Program listings are formatted as follows:

```
class Test {
    public static void main(String [] args) {
        System.out.println("This is a program listing.");
    }
}
```

3. Accessing Documentation Online

ForgeRock publishes comprehensive documentation online:

 The ForgeRock Knowledge Base offers a large and increasing number of up-to-date, practical articles that help you deploy and manage ForgeRock software.

While many articles are visible to community members, ForgeRock customers have access to much more, including advanced information for customers using ForgeRock software in a mission-critical capacity.

• ForgeRock product documentation, such as this document, aims to be technically accurate and complete with respect to the software documented. It is visible to everyone and covers all product features and examples of how to use them.

4. Using the ForgeRock.org Site

The ForgeRock.org site has links to source code for ForgeRock open source software, as well as links to the ForgeRock forums and technical blogs.

If you are a *ForgeRock customer*, raise a support ticket instead of using the forums. ForgeRock support professionals will get in touch to help you.

5. Getting Support and Contacting ForgeRock

ForgeRock provides support services, professional services, training through ForgeRock University, and partner services to assist you in setting up and maintaining your deployments. For a general overview of these services, see https://www.forgerock.com.

ForgeRock has staff members around the globe who support our international customers and partners. For details on ForgeRock's support offering, including support plans and service level agreements (SLAs), visit https://www.forgerock.com/support.



Chapter 1 IG At a Glance

This chapter provides a quick look at what is available in IG. For more information about the features of IG, see "About Identity Gateway" in the Gateway Guide.

Most organizations have valuable existing services that are not easily integrated into newer architectures. These existing services cannot often be changed. Many client applications cannot communicate as they lack a gateway to bridge the gap. "Missing Gateway" illustrates one example of a missing gateway.


Missing Gateway

Client Client Client request not appropriate for service 2 Service response not appropriate for client Client Service

IG works as an HTTP gateway, based on reverse proxy architecture. IG is deployed on a network so it can intercept both client requests and server responses. "IG Deployed" illustrates a IG deployment.



IG Deployed



Clients interact with protected servers through IG, which can be configured to add new capabilities to existing services without affecting current clients or servers.

The following list includes features that you can add to your solution by using IG:

- Access management integration
- · Application and API security
- · Credential replay
- OAuth 2.0 support
- OpenID Connect 1.0 support
- · Network traffic control
- · Proxy with request and response capture
- · Request and response rewriting
- SAML 2.0 federation support
- SSO



Chapter 2 First Steps

This chapter describes how to quickly set up an instance of IG and use it as a gateway to access a sample application.

2.1. Software Requirements

- Java Development Kit (JDK): For information about supported web application containers, see "JDK Version" in the *Release Notes*
- **Apache Tomcat** or **Jetty**: For information about supported versions of JDK, see "Web Application Containers" in the *Release Notes*.

2.2. Configuring the Network

Because IG uses reverse proxy architecture, you must configure the network so that traffic from the browser to the sample application goes through IG.

In this guide, IG and a sample application run on the same host as your browser, which is probably your laptop or desktop. Because network configuration is an important deployment step, the configuration in this chapter expects the sample application to run on app.example.com rather than localhost.

The quickest way to configure the network locally is to add an entry to your etc/hosts file on UNIX systems or %SystemRoot%\system32\drivers\etc\hosts on Windows. For more information about host files, see the Wikipedia entry, Hosts (file).

Edit your /etc/hosts file as follows:

• To run the browser, IG, and the sample application on the same host, add the following entry:

```
127.0.0.1 localhost openig.example.com app.example.com
```

• To run the browser on one host, and IG and the sample application on another host, add the IP address of the host running IG and the sample application to the hosts file on the system running the browser, where the host name matches that of sample application. For example, if IG and the sample application are running on a host with IP address 192.168.0.15, add the following entry:

```
192.168.0.15 openig.example.com app.example.com
```



• To run the sample application on a different host to IG, also make sure that the host name of the sample application resolves correctly for requests from IG to the application.

Tip

• Some browsers cache IP address resolutions, even after clearing all browsing data. After changing the IP addresses of named hosts, restart the browser.

To make sure DNS or host settings are configured correctly for remote systems, stop IG and then make sure you cannot reach the target application with the host name and port number of IG. If you can still reach it, double-check your host settings.

• Make sure that name resolution is configured to check host files before DNS. For most UNIX systems, make sure that files is listed before dns in /etc/nsswitch.conf.

2.3. Installing IG

IG is installed in the root context of a web application container. For information about supported web application containers, see "Web Application Containers" in the *Release Notes*.

This guide uses Jetty server. The example commands assume you install Jetty to <code>/path/to/jetty</code>, and after installation, you have a directory <code>/path/to/jetty/webapps</code> in which you install IG. If you use another directory structure, substitute the commands.

To Install IG

- Download a supported version of Jetty server from its download page, and install it to /path/to/jetty.
- 2. Download IG-5.5.2.war from the ForgeRock BackStage download site.
- 3. Copy (or move) and rename the .war file:

```
$ cp IG-5.5.2.war /path/to/jetty/webapps/root.war
```

Jetty automatically deploys IG in the root context on startup.

- 4. Start Jetty:
 - To start Jetty in the background, enter:

```
$ /path/to/jetty/bin/jetty.sh start
```

• To start Jetty in the foreground, enter:

```
$ cd /path/to/jetty/
$ java -jar start.jar
```



- 5. Make sure that IG is running:
 - Make sure you can see the IG welcome page at http://localhost:8080.

When you start IG without a configuration, requests to IG default to a welcome page with a link to the documentation.

• Make sure that you can see IG Studio at http://localhost:8080/openig/studio.

For more information about IG Studio, see "Configuring Routes With IG Studio".

• Display the product version and build information at http://localhost:8080/openig/api/info.

2.4. Installing the Sample Application

ForgeRock provides a mockup web application for testing IG configurations. The sample application is used in many of the tutorials in this guide and the *Gateway Guide*. This section describes how to download and run the sample application.

Installing the Sample Application

- Download the sample application, IG-sample-application-5.5.2.jar, from the ForgeRock BackStage download site.
- 2. Run the sample application:

```
$ java -jar IG-sample-application-5.5.2.jar
Preparing to listen for HTTP on port 8081.
Preparing to listen for HTTPS on port 8444.
The server will use a self-signed certificate not known to browsers.
When using HTTPS with curl for example, try --insecure.
Using OpenAM URL: http://openam.example.com:8088/openam/oauth2.
Starting server...
Sep 09, 2016 9:52:56 AM org.glassfish.grizzly.http.server.NetworkListener start
INFO: Started listener bound to [0.0.0.0:8444]
Sep 09, 2016 9:52:56 AM org.glassfish.grizzly.http.server.NetworkListener start
INFO: Started listener bound to [0.0.0.0:8081]
Sep 09, 2016 9:52:56 AM org.glassfish.grizzly.http.server.HttpServer start
INFO: [HttpServer] Started.
Press Ctrl+C to stop the server.
```

By default, this server listens for HTTP on port 8081, and for HTTPS on port 8444. If one or both of those ports are not free, specify other ports:



```
$ java -jar IG-sample-application-5.5.2.jar 8888 8889
Preparing to listen for HTTP on port 8888.
Preparing to listen for HTTPS on port 8889.
The server will use a self-signed certificate not known to browsers.
When using HTTPS with curl for example, try --insecure.
Using OpenAM URL: http://openam.example.com:8088/openam/oauth2.
Starting server...
Sep 09, 2016 9:55:57 AM org.glassfish.grizzly.http.server.NetworkListener start
INFO: Started listener bound to [0.0.0.0:8889]
Sep 09, 2016 9:55:57 AM org.glassfish.grizzly.http.server.NetworkListener start
INFO: Started listener bound to [0.0.0.0:8888]
Sep 09, 2016 9:55:57 AM org.glassfish.grizzly.http.server.HttpServer start
INFO: [HttpServer] Started.
Press Ctrl+C to stop the server.
```

If you change the port numbers when starting the server, also account for the differences when using the examples.

3. Browse to http://localhost:8081/home to access the home page of the sample application.

Some information about the browser request is displayed.

4. Browse to http://localhost:8081/login to access the login page of the sample application, and then log in with username demo and password changeit.

The username, demo, and some information about the browser request is displayed.

Stopping and Restarting IG

- 1. Stop Jetty:
 - If Jetty is running in the background, enter:

```
$ /path/to/jetty/bin/jetty.sh stop
```

- If Jetty is running in the foreground, enter Ctrl+c in the terminal where Jetty is running.
- 2. Start Jetty:
 - To start Jetty in the background, enter:

```
$ /path/to/jetty/bin/jetty.sh start
```

• To start Jetty in the foreground, enter:

```
$ cd /path/to/jetty/
$ java -jar start.jar
```



2.5. Trying IG With a Simple Configuration

2.5.1. Adding a Base Configuration File

The entry point for requests coming in to IG is a JSON-encoded configuration file, expected by default at \$HOME/.openig/config/config.json.

If IG doesn't find \$HOME/.openig/config/config.json at startup, it uses its own, default config.json.

The config.json file initializes a heap of objects and provides the main Handler to receive incoming requests. For more information, see Heap Objects(5) in the *Configuration Reference* and Router(5) in the *Configuration Reference*.

If you edit config. json, stop and restart IG to take the changes into effect.

By default, the router defined in config.json looks for routes in \$HOME/.openig/config/routes. For more information, see GatewayHttpApplication(5) in the Configuration Reference

Neither \$HOME/.openig/config nor \$HOME/.openig/config/routes are created automatically.

To Configure the Base Configuration of IG

1. Add the following file to the IG configuration as \$HOME/.openig/config.json, on Windows add the file as %appdata%\OpenIG\config\config.json:

```
{
  "handler": {
    "type": "Router",
    "name": "_router",
    "baseURI": "http://app.example.com:8081",
    "capture": "all"
 },
  "heap": [
      "name": "JwtSession",
      "type": "JwtSession"
      "name": "capture",
      "type": "CaptureDecorator",
      "config": {
        "captureEntity": true,
        "_captureContext": true
   }
 ]
```

Notice the following features of the file:



- The handler contains a main router named <u>router</u>. When IG receives an incoming request, <u>router</u> routes the request to the first route in the configuration whose condition is satisfied.
- The baseURI changes the request URI to point the request to the sample application.
- The capture captures the body of the HTTP request and response.
- 2. Stop and restart IG, as described in "Stopping and Restarting IG".

The Jetty log includes a message that the config is loaded from the new file:

```
INFO o.f.openig.web.Initializer -
Reading the configuration from $HOME/.openig/config/config.json
```

To locate the <code>%appdata%</code> folder for your version of Windows, open Windows Explorer, enter <code>%appdata%</code> as the file path, and press Enter. You must create the <code>%appdata%\OpenIG\config</code> folder, and then copy the configuration files.

Before you use this base configuration in production, adjust the log level, and deactivate the CaptureDecorator that generates several log message lines for each request and response. Also consider editing the router based on recommendations described in "Preventing the Reload of Routes" in the *Gateway Guide*.

Important

If you plan to create routes through IG Studio, make sure that config.json contains a main router named router. For information about IG Studio, see "Configuring Routes With IG Studio".

2.5.2. Adding a Default Route

To Configure a Default Route

 Add the following file to the IG configuration as \$HOME/.openig/config/routes/zz-default.json, on Windows add the file as %appdata%\OpenIG\config\routes\zz-default.json:

```
{
    "handler": "ClientHandler"
}
```

The Jetty log includes a message that the new file is loaded into the config:

```
INFO o.f.o.handler.router.RouterHandler -
Loaded the route with id 'zz-default' registered with the name 'zz-default'
```

Notice the following features of the route:



- The route calls a ClientHandler with the default configuration. The ClientHandler simply proxies the request to the sample application and returns the response, without changing either the request or the response.
- Because routes are loaded lexicographically in the configuration, firstly by name and then by ID, the filename of the default route is zz-default.json. Using a filename that starts with zz almost guarantees that the default route is the last route in the configuration, and therefore the last route to which requests are directed.

2.5.3. Testing the Setup

To test your configuration, make sure that IG and the sample application are running, and then browse to http://openig.example.com:8080/home. You should be directed to the home page of the sample application.

What just happened:

- When you browsed to http://openig.example.com:8080/home, you connected to IG deployed in Jetty.
- The baseURI in config.json changed the request URI to point the request to the sample application, and the capture captured the body of the HTTP request and response.

The main router in config. json routed the request to the IG configuration.

- Because there was no other route in the IG configuration, the request was routed to zz-default.json. This default route called a ClientHandler, which submitted the request to the sample application and returned the response without changing either the request or the response.
- The browser request was sent unchanged to the sample application, and the response from the sample application was returned unchanged to the browser.


2.6. Adding a Route to the IG Configuration

In the previous section you set up IG to proxy requests to the home page of the sample application. In this section, you add a route to log you in to the sample application automatically.

"Log in With Hard-Coded Credentials" shows the steps to log in to the sample application by using hard-coded credentials.



Log in With Hard-Coded Credentials



- 1. The browser host makes a DNS request for the IP address of the HTTP server host, openig.example
- 2. DNS responds with the address for IG.
- 3. Browser sends a request to the HTTP server.
- 4. IG replaces the browser's original HTTP GET request with an HTTP POST login request containing credentials to authenticate. As a result, instead of returning the login page with a login form, IG logs you in directly.
- 5. The sample application responds with the page you see after logging in.
- 6. IG returns this response to your browser.

2.6.1. Configuring IG to Log You In With Credentials

To Configure IG to Log You In With Credentials

 Add the following file to the IG configuration as \$HOME/.openig/config/routes/01-static.json, on Windows add the file as %appdata%\OpenIG\config\routes\01-static.json:



The Jetty log includes a message that the new file is loaded into the config:

```
INFO o.f.o.handler.router.RouterHandler -
Loaded the route with id '01-static' registered with the name '01-static'
```

By default, routes in the \$HOME/.openig/config/routes directory are loaded and updated without restarting IG.

Because routes are loaded lexicographically in the configuration, firstly by name and then by ID, <code>Ol-static.json</code> is loaded into the configuration before <code>zz-default.json</code>.

2.6.2. Testing the Setup

To test your configuration, make sure that IG and the sample application are running, and then browse to http://openig.example.com:8080/static. You should be directed to the sample application and logged in automatically as demo.

What just happened:

- When you browsed to http://openig.example.com:8080/static, you connected to IG deployed in Jetty, and the request was routed to 01-static.json.
- The StaticRequestFilter replaced the request with an HTTP POST request, including the login form with hard-coded credentials.
- The sample application validated the credentials, and responded with the profile page.
- The ClientHandler proxied the request to the sample application and returned the response.
- IG passed the response back to the browser.



Chapter 3

Configuring Routes With IG Studio

IG Studio is a user interface to configure and deploy routes in IG. IG Studio provides an easy way to evaluate or demo IG, or to develop new configurations on a single instance.

You can use IG Studio to create routes for many applications, such as authenticating users, authorizing access to APIs, throttling requests to protected applications, capturing messages, and collecting statistics.

IG Studio runs only when IG is in development (mutable) mode. When IG is in production (immutable) mode you cannot change your configuration. In this mode, IG Studio is effectively disabled. For more information about production and development modes, see "Making the Configuration Immutable" in the *Gateway Guide*.


Important

IG Studio deploys and undeploys routes through a main router named <u>router</u>, which is the name of the main router in the default configuration. If you use a custom <u>config.json</u>, make sure that it contains a main router named <u>router</u>.

3.1. Accessing IG Studio

When IG is installed and running as described in "First Steps", access IG Studio on http://openig.example.com:8080/openig/studio. The welcome screen is displayed.





The following tables summarize the basic tasks in IG Studio, and the route status:

Task Reference

To do this	Do this	
Create a new route	Select A ROUTES or • Protect an Application, and start creating a new route.	
Select a route	Select A ROUTES, and then select a route to view.	
Display the config of a selected route	Select a route, and then select and 🗗 Display.	
Deploy a selected route	Select a route, and then select Deploy.	
Undeploy a selected route	Select a deployed route, and then select : and ★ Undeploy.	
Change the basic config of a selected route	Select a route, and then select & Route settings. Edit the route and save the changes.	



Route Status

Status	Description	Action
❸ Undeployed	The route has been created and saved in IG Studio or has been imported into IG Studio, but does not exist in the backend.	Deploy the route. The status changes to Deployed.
Deployed	The route is saved in IG Studio and deployed to the backend.	No action required. The route has the same configuration in IG Studio and the backend.
❸ Changes pending	The route has been deployed and then subsequently changed in IG Studio.	Deploy the route. The status changes to ♥ Deployed.
▲ Out of sync	The route has been deployed and then subsequently changed in the backend, or in both IG Studio and the backend.	Select Deploy. A message informs you that a different version of the route is deployed in the backend. Select Deploy or LIMPORT a route.
		△ Deploy : The version in IG Studio overwrites the backend.
		♣ Import a route : The version in the backend overwrites IG Studio.
		When you import a route into IG Studio you go into editor mode . You can use the JSON editor to manually edit the route, but can no longer use the full IG Studio interface to add or edit filters.

3.2. Creating Simple Routes

This section describes procedures to configure the basic settings for a route in IG Studio. After creating a route, you can always edit its basic settings by selecting & Route settings on the top-right of the screen.

To Create a Simple Route

This procedure bypasses some of the steps of "To Create a Route With Advanced Options" by using a path condition, and matching the route name to the condition.

 Access IG Studio on http://openig.example.com:8080/openig/studio, and select Protect an Application.



2. In Application URL, enter a URL for the application you want to protect followed by a path condition, and then select Create route.

For example, to allow requests to access the sample application on the my-basic-route path, enter http://app.example.com:8081/my-basic-route.

3. On the top-right of the screen, select **:** and **☑** Display.

A route similar to this should be displayed, where the path condition is used for the route name:

```
{
   "name": "my-basic-route",
   "baseURI": "http://app.example.com:8081",
   "condition": "${matches(request.uri.path, '^/my-basic-route')}",
   "monitor": false,
   "handler": "ClientHandler"
}
```

To Create a Route With Advanced Options

- 1. Access IG Studio on http://openig.example.com:8080/openig/studio, and select ♠ Protect an Application.
- 2. In the Create a route window, enter a URL for the application you want to protect, and then select Create route. For example, to protect the sample application, enter http://app.example.com:8081.
- 3. (Optional) In Condition, select Path or Expression, and then enter a condition for the route. For example, to allow only requests on the path /mypath, select Path and enter /mypath.

The route can handle requests that meet the condition you specify. If you don't specify a condition, the route can handle all requests.

For information about route conditions, see "Setting Route Conditions" in the Gateway Guide.

4. In Name, enter a unique name for the route. The name is used to order the routes lexicographically in the configuration. For example, enter the name my route.

The route ID is filled automatically when you enter a name, and any spaces are replaced by dashes. You can change the name and ID independently. For information about how route names, IDs, and filenames are used in the configuration, see " Configuring Route Names, IDs, and Filenames " in the *Gateway Guide*.

5. Select Create route, and then on the top-right of the screen, select and 🗹 Display.

A route similar to this should be displayed:



```
{
  "name": "my route",
  "baseURI": "http://app.example.com:8081",
  "condition": "${matches(request.uri.path, '^/mypath')}",
  "monitor": false,
  "handler": "ClientHandler"
}
```

3.3. Deploying Routes to Your Configuration

After creating or importing a route in IG Studio, deploy it to you IG configuration for testing.

To Deploy a Route to Your Configuration

- 1. In IG Studio, select A ROUTES and then select a route.
- 2. On the top-right of the screen, select: and 🗷 Display, and then check the configuration. If the route is okay, select 🐧 Deploy to push the route to the IG configuration.
 - The route status ♥ Deployed is displayed, and the ♠ Deploy button is grey and disabled.
- 3. Check the \$HOME/.openig/config/routes folder in your IG configuration to see that the route is there.
 - By default, routes are loaded automatically into the IG configuration. You don't need to stop and restart IG. For information about reloading routes, see "Preventing the Reload of Routes" in the *Gateway Guide*.
- 4. Check the system log messages to confirm that the route was loaded successfully into the configuration. For information about logs, see "Logging Events" in the Gateway Guide.

To Undeploy a Route

- 1. In IG Studio, select A ROUTES and then select a route.
- 2. On the top-right of the screen, select: and * Undeploy, and then confirm your request.

The route is removed from the IG configuration. On the IG Studio screen, the route status
Deployed is no longer displayed, and the Deploy option is active again.

3.4. Adding Filters to a Route

For routes created in IG Studio, you can use the full interface of IG Studio to add filters. For examples, see the following sections of the *Gateway Guide*:

• For authentication and authorization, see "Enforcing Policy Decisions and Supporting Session Upgrade" in the Gateway Guide and "Acting as an OAuth 2.0 Resource Server" in the Gateway Guide.



- For throttling, see "Throttling the Rate of Requests to Protected Applications" in the Gateway Guide.
- For scriptable filters, reference scripts, and scriptable throttling rates, see "Creating a ScriptableFilter in IG Studio" in the *Gateway Guide* and "Configuring a Scriptable Throttling Filter "in the *Gateway Guide*.

Filters are added to a chain that ends with a ClientHandler. To view the chain, select **%** Chain on the right of the screen. For information about chains, see Chain(5) in the *Configuration Reference*.

Note the following ways to manage filters in a chain:

- To move a filter to another position in the chain, simply drag it.
- To edit a filter in the chain, select *p* for the filter.
- To remove a filter from the chain, deselect ENABLED. The filter is disabled and removed from the chain. If you enable the filter again, the configuration is restored, and you don't have to enter the data again.
- To add a disabled filter back in the chain, select ENABLED.

To Add Other Filters to a Route

- 1. In IG Studio, select A ROUTES and then select a route.
- 2. Select ↑ Other filters, **+** New filter, and then Other filter.
- 3. In Type, select a filter type from the list, and then optionally enter a name and configuration for the filter.

Note

IG Studio checks that the JSON is valid, but doesn't check that the configuration of the filter is valid. If the filter configuration isn't valid, the route fails to load when deployed.

When you save, the filter is added to the chain.

4. Deploy the route as described in "Deploying Routes to Your Configuration".

3.5. Editing and Redeploying Routes

To Edit and Redeploy a Route

1. In IG Studio, select A ROUTES and then select a route.



- 2. Edit the route in IG Studio or manually:
 - To edit in IG Studio, select options offered in IG Studio.
 - To edit manually, select: and A Editor mode, and use the JSON editor to edit the route.

Important

When you go into **editor mode**, you can use the JSON editor to manually edit the route, but can no longer use the full IG Studio interface to add or edit filters.

The route status is **6** Changes pending.

3. Deploy the route as described in "To Deploy a Route to Your Configuration".

3.6. Importing Routes Into IG Studio

Important

When you import a route into IG Studio you go into **editor mode**. You can use the JSON editor to manually edit the route, but can no longer use the full IG Studio interface to add or edit filters.

To Import a Route Into IG Studio

- In IG Studio, select A ROUTES and then select a route.
- 2. Click in the window to import a route, or drag a route from your filesystem.

If the route has a name property, the name is automatically used for the Name and ID fields in IG Studio.

- 3. If necessary, make the following changes, and then select Import:
 - If the Name and ID fields are empty, enter a unique name and ID for the route.
 - If the Name and ID fields are outlined in red, the route name or ID already exists in IG Studio. Change the name and ID to be unique.
 - If an error message is displayed, the route is not valid JSON. Fix the route and then try again to import it.

The route is displayed in the editor window.

4. Deploy the route as described in "Deploying Routes to Your Configuration".



3.7. Viewing and Searching for Routes in Your Configuration

All of the routes that exist in your backend configuration are displayed on the # ROUTES page, including imported routes and routes created outside of IG Studio.

To search for a route, select \triangle ROUTES, and type part of the name or URL of the route in the search box (\mathbb{Q}). Routes that match are displayed as you enter the search criteria.